

Standard Image Processing

This option requires a dark background with adequate lighting conditions as shown in Figure 1. There should be no objects in the background besides the (left-most) reference object if it is used and the potatoes. Figure 2 shows a situation where the processing would have difficulty due to the lighting conditions and surface reflections.



Figure 1: Optimal Standard Processing Conditions



Figure 2: Inadequate Standard Processing Conditions

Machine Learning Processing

This option is designed to work on a variety of **basic** varying backgrounds such as soil, grass, concrete, as well as varying lighting conditions. Some other objects in the image should be ok. Figure 3 shows an example of when this option would be used.



Figure 3: Machine Learning Processing Use-Case Scenario

Reference Object

Note that regardless of what processing method is used, if a reference object is selected the image must be set against a dark background with no other objects in the background besides potatoes. The reference object used must be a coin, preferably a quarter or dime, set at the left-most object in the image. If no reference object is used, the data will be returned in units of pixels, the L/W ratio will still be accurate.



Extracting Data

After processing, a .txt file will be added to the android documents folder with the processed data, as shown in Figure 4.




Figure 4: Processed data location

The processed data in each .txt file follows this format:

- 1. Number of potatoes
- 2. Minimum L/W
- 3. Maximum L/W
- 4. Average L/W
- 5. Reference object used
- 6. Potato #1 length
- 7. Potato #1 width
- 8. Potato #1 L/W
- 9. Potato #2 length
- 10. Potato #2 width
- 11. Potato #2 L/W
- 12.

\leftarrow	2021-04-19-00-50-35-7.txt
10	
1.21	
1.69	
1.46	
None	
1015.57	
641.05	
1.58	
1061.01	
670.6	
1.58	
1085.0	
643.0	
1.69	
987.74	
623.03	
1.59	